

| | | | | | | |
|----------|---------------------|-----------------------------------|-----|--------|-------------|-----------------------------------|
| 78003539 | DEFB 78003539 | ;toni B - B+ | A#+ | 46 | LD B, (HL) | ;B = podatek za ustrezno noto |
| | | ;tipke M K I B | | BB | CP B | ;primerjaj B z 0 |
| 6962CFDD | DEFB 6962CFDD | ;toni C# D# D | D | 28E5 | JR Z, ZANKA | ;nazaj, če tipka ne predstavlja |
| | | ;tipke 3 E D X | X | | | ;nobene note |
| 70003200 | DEFB 70003200 | ;toni C+ - C++ | - | 79 | LD A, C | ;A = barva roba ekrana, bit 4 = 1 |
| | | ;tipke sym L O 9 | 9 | C5 | PUSH BC | |
| 0070ECFD | DEFB 0070ECFD | ;toni - C+ C# C | C | CDXXXX | CALL TON | ;prva polovica ciklusa note |
| | | ;tipke 2 W S Z | Z | C1 | POP BC | |
| 00000000 | DEFB 00000000 | ;toni - - - | - | E607 | AND 7 | ;bit 4 = 0 |
| | | ;tipke spc ent P O | O | CDXXXX | CALL TON | ;druga polovica ciklusa note |
| 00000000 | DEFB 00000000 | ;toni - - - | - | 1B | JR ZANKA | |
| | | ;tipke 1 Q A caps | A | FB | KONEC EI | |
| 00 | TON | ;ta podprogram povzroči premor | | C9 | RET | |
| 00 | | ;točno določene dolžine | | | | |
| 10FB | DJNZ TON | | | | | |
| D3FE | OUT (#FE), A | ;oddaj impulz (en element žele- | | | | |
| C9 | RET | ;nega tona) | | | | |
| 3A485C | START LD A, (#5C48) | ;daj v A podatek o robu zaslona | | | | |
| CB1F | RRA | | | | | |
| CB1F | RRA | | | | | |
| CB1F | RRA | | | | | |
| E607 | AND 7 | ;A = barva roba | | | | |
| F610 | OR #10 | ;da bitu 4 vrednost 1 | | | | |
| 4F | LD C, A | | | | | |
| F3 | DI | ;potek naj bo brez prekinitev | | | | |
| C5 | ZANKA PUSH BC | | | | | |
| CD8E02 | CALL #028E | ;= CALL KEY SCAN. V DE bo podatek | | | | |
| C5 | POP BC | ;o tipkovnici | | | | |
| 212027 | LD HL, #2720 | ;HL = kod "caps shift + space" | | | | |
| A7 | AND A | | | | | |
| ED52 | SBC HL, DE | | | | | |
| 2B1A | JR Z, KONEC | ;končaj, če je pritisnjen BREAK | | | | |
| 7B | LD A, E | ;podatek o pritisnjeni tipki brez | | | | |
| 3C | INC A | ;shiftov | | | | |
| 2BEF | JR Z, ZANKA | ;nazaj, če ni pritisnjena nobena | | | | |
| AF | XOR A | ;tipka | | | | |
| 57 | LD D, A | ;DE = podatek o pritisnjeni tipki | | | | |
| | | ; (brez shiftov) | | | | |
| 21XXXX | LD HL, NOTE | | | | | |
| 19 | ADD HL, DE | ;HL = naslov note v tabeli | | | | |