

RSX-11M V3.2
UTILITIES
BRU

Seq 5.1.17.14 M

5 of 5

TOTSIZ: .BLKW 2 ; TOTAL SIZE OF FILE (# OF BLOCKS)

.END

Assemble BRUHEAD.PAT to create BRUHEAD.POB.

```
>SET /UIC=[74,40]
>MAC BRUHEAD.POB=BRUHEAD.PAT
```

Extract the module BRUHEAD.OBJ from [1,20]BRU.OLB, apply the patch, assign TK: to your target output device, and build BRU.

```
>LBR BRUHEAD.OBJ;1=[1,20]BRU/EX:BRUHEAD
>PAT BRUHEAD.OBJ;2=BRUHEAD.OBJ;1/CS:27167,BRUHEAD.POB/CS:72337
>SET /UIC=[1,20]
>LBR BRU/RP=[74,40]BRUHEAD.OBJ;2
>ASN ddn:=TK:
>TKB @ [1,24]BRU.BLD
```