

RSX-11M V3.2
 UTILITIES
 BRU

Seq 5.1.17.13 M

2 of 5

```

;
      .IDENT /01.1/

      .MCALL DIRS,WTSE$$

      .PSECT

      .BLK.=.

; OUTPUT CORRECT MSG IF TAPE DRIVER NOT LOADED

      .=.BLK.+36
      BCS      15$          ; HANDLER NOT RESIDENT
      NOP

      .=.BLK.+56
      15$:

; WAIT FOR DETACHES TO COMPLETE
; MAKE TAPEIO SERIALLY REUSABLE

      .=.BLK.+3570

      CALL     PAT1          ; CALL PATCH
      DIRS     $SOUDP8      ; DETACH THE OUTPUT DISK
      BCS      30$          ; DON'T WAIT IF DETACH FAILS
      WTSE$$   #EFN2        ; WAIT FOR OUTPUT DETACH
30$:      RETURN           ; DONE HERE

; CORRECT "MOUNT TAPE..." MESSAGE

CF.MES = 1000

      .=.BLK.+1170

      JMP      PAT2          ; JUMP TO PATCH
      .REPT   6
      NOP
      .FNDR

      .=.BLK.+1210

RWD1::

      .=.BLK.+1232

RWD2::

      .=.BLK.+1500

      .REPT   3
      NOP
      .FNDR

```